

---

# ORB-Python Documentation

**Nils Hoffmann**

**Nov 08, 2024**



# CONTENTS

<b>1</b>	<b>Python API</b>	<b>3</b>
1.1	devices . . . . .	3
1.1.1	sensor . . . . .	3
1.1.2	motor . . . . .	4
1.1.3	servo . . . . .	6
1.2	memory . . . . .	6
1.3	time . . . . .	7
1.4	monitor . . . . .	7
<b>2</b>	<b>VM API</b>	<b>9</b>



Welcome to the documentation of the **ORB-Python** project.



## PYTHON API

This part of the Documentation is the Python API. Here you can find how to program your Open Robotics Board using Python.

### 1.1 devices

The Devices Module allows you to program the ORBs configurable peripherals as well as onboard devices.

#### 1.1.1 sensor

The *Sensor* class represents a sensor device with configurable parameters and multiple data retrieval methods.

**class** `devices.sensor(port: int, type: int, mode: int, option: int)`

Initializes a sensor instance connected to a specified port with defined type, mode, and optional parameters.

##### Parameters

- **port** (*int*) – The port number the sensor is connected to.
- **type** (*int*) – Type of the sensor, such as *Analog*, *I2C*, *TOF*, *Touch*, or *UART*.
- **mode** (*int*) – Operating mode of the sensor.
- **option** (*int*) – Additional configuration option.

**config**(*type: int, mode: int, option: int*)

Configures the sensor.

##### Parameters

- **type** (*int*) – Type of the sensor (*Analog*, *I2C*, *TOF*, *Touch*, or *UART*).
- **mode** (*int*) – Operating mode of the sensor.
- **option** (*int*) – Additional configuration option.

**get**() → Dict["values": [int ,int], "type": int, "option": int, "lenExp": int]

Retrieves the sensor report as a dictionary representation.

**getDigital**() → int

Returns a digital reading from the sensor.

##### Returns

The digital value.

**Return type**

int

**getValueExt**(*channel: int*) → int**Parameters****channel** (*int*) – The channel number to retrieve the value from.**Returns**

The value from the specified channel.

**Return type**

int

**Ports****S1 = 0**

Sensor port 1.

**S2 = 1**

Sensor port 2.

**S3 = 2**

Sensor port 3.

**S4 = 3**

Sensor port 4.

**Types****Analog = 0**

Analog sensor type.

**I2C = 1**

I2C sensor type.

**TOF = 2**

Time-of-Flight sensor type.

**Touch = 3**

Touch sensor type.

**UART = 4**

UART sensor type.

### 1.1.2 motor

The *Motor* class represents a motor device with configurable parameters and various modes of operation.

**class** `devices.motor`(*port: int, direction: int, ticks: int, acc: int, kp: int, ki: int*)

Initializes a motor instance.

**Parameters**

- **port** (*int*) – The port that the motor is connected to.
- **direction** (*int*) – Direction of the motor (*FORWARD* or *REVERSE*.)
- **ticks** (*int*) – Number of encoder ticks for one revolution.
- **acc** (*int*) – Acceleration rate of the motor.



- **kp** (*int*) – Proportional gain for the motor control.
- **ki** (*int*) – Integral gain for the motor control.

**config**(*direction: int, ticks: int, acc: int, kp: int, ki: int*)

Configures the motor parameters.

#### Parameters

- **direction** (*int*) – Direction of the motor, either *FORWARD* or *REVERSE*.
- **ticks** (*int*) – Number of encoder ticks for one revolution.
- **acc** (*int*) – Acceleration rate.
- **kp** (*int*) – Proportional gain.
- **ki** (*int*) – Integral gain.

**set**(*mode: int, speed: int, position: int*)

Sets the motor's operating mode, speed, and position.

#### Parameters

- **mode** (*int*) – The mode in which to operate the motor (*POWER\_MODE*, *BRAKE\_MODE*, *SPEED\_MODE*, or *MOVETO\_MODE*).
- **speed** (*int*) – The speed of the motor.
- **position** (*int*) – The target position for the motor.

**get**() → Dict["speed": int, "power": int, "position": int]

#### Returns

A dictionary containing: - **speed**: The current speed. - **power**: The current power. - **position**: The current position.

#### Ports

**M1** = 0

Motor port 1.

**M2** = 1

Motor port 2.

**M3** = 2

Motor port 3.

**M4** = 3

Motor port 4.

#### Modes

**FORWARD** = 1

**REVERSE** = -1

**POWER\_MODE** = 0

**BRAKE\_MODE** = 1

**SPEED\_MODE** = 2

**MOVETO\_MODE** = 3

### 1.1.3 servo

The *Servo* class represents a servo device with specific parameters.

**class** `devices.servo(port: int)`

A servo object.

**Parameters**

**port** (*int*) – The port number the servo is connected to.

**set**(*speed: int, angle: int*)

Sets the speed and angle for the servo.

**Parameters**

- **speed** (*int*) – Speed of the servo movement.
- **angle** (*int*) – Target angle for the servo.

**Ports**

**S1**

Servo port 1.

**S2**

Servo port 2.

## 1.2 memory

The *memory* module provides functions to manage memory operations.

**memory.setMemory**(*addr: int, data: list | bytes*)

Sets memory at the specified address with the given data.

**Parameters**

- **addr** (*int*) – The memory address to set.
- **data** (*list | bytes*) – The data to be stored, which can be a list or bytes.

**memory.getMemory**(*addr: int, length: int*) → bytes

Returns memory starting from the specified address in the user-memory-region.

**Parameters**

- **addr** (*int*) – The starting memory address.
- **length** (*int*) – The number of bytes to retrieve.

**Returns**

The retrieved memory content as bytes.

**Return type**

bytes

**memory.clearMemory**()

Clears all stored memory data.

## 1.3 time

The *time* module provides utilities for working with time, including retrieving the current time and introducing delays.

`time.getTime()` → int

Returns the time, since microcontroller start.

**Returns**

The current time in milliseconds.

**Return type**

int

`time.wait(ms: int)`

Pauses execution for a given number of milliseconds.

**Parameters**

**ms** – Number of milliseconds to wait.

**Type**

int

## 1.4 monitor

The *monitor* module provides functionality for ORB-Monitor communication.

`monitor.getKey()` → int

**Returns**

Current key pressed on the monitor.

**Return type**

int

`monitor.setText(text: str)`

Sets the text to be displayed on the monitor. At the Moment only 32 characters are supported for one Line.

**Parameters**

**text** (*str*) – The text to display.

**class** `monitor.keys`

A class representing key constants for the *monitor*.

Each key constant has a unique integer value.

**Available keys:**

- **NO\_KEY** = 0
- **A1** = 1
- **A2** = 2
- **A3** = 3
- **A4** = 4
- **A5** = 5
- **A6** = 6

- **A7** = 7
- **A8** = 8
- **B1** = 9
- **B2** = 10
- **B3** = 11
- **B4** = 12
- **B5** = 13
- **B6** = 14
- **B7** = 15
- **B8** = 16
- **B9** = 17
- **B10** = 18
- **B11** = 19
- **B12** = 20
- **C1** = 21

## VM API

class **PythonVM**

A class to manage the Micropython-VirtualMachine. Providing methods for running, stopping, and retrieving the VM's status.

void **PythonVM::run**(LoadLengthFunction loadLength, LoadProgramFunction loadProgram, uint8\_t arg)

Starts the VM with the specified load functions and argument.

**Parameters**

- **loadLength** – Function pointer that returns the program length
- **loadProgram** – Function pointer that loads the program data
- **arg** – Additional argument passed to the program

bool **PythonVM::isRunning**()

Checks if the VM is currently running.

**Returns**

True if the VM is running, otherwise False

**Rtype**

bool

void **PythonVM::stopProgram**()

Stops the currently running program in the VM.

int **PythonVM::getExitStatus**()

Retrieves the exit status of the VM.

**Returns**

Exit status code

**Rtype**

int

const char \***PythonVM::getExitInfo**()

Returns additional information about the VM's exit status.

**Returns**

Exit information string

**Rtype**

const char\*

### enum **Status**

Enumeration for VM exit statuses, indicating various exit conditions.

#### **Status codes:**

- **NORMAL**: Program exited normally.
- **EXCEPTION**: Program exited with an exception.
- **INTERRUPT**: Program was interrupted by User.

## INDEX

- \spxentrybuilt-in function
  - \spxentrymemory.clearMemory(), 6
  - \spxentrymemory.getMemory(), 6
  - \spxentrymemory.setMemory(), 6
  - \spxentrymonitor.getKey(), 7
  - \spxentrymonitor.setText(), 7
  - \spxentrytime.getTime(), 7
  - \spxentrytime.wait(), 7
- \spxentryconfig()\spxextradevices.motor method, 5
- \spxentryconfig()\spxextradevices.sensor method, 3
- \spxentrydevices.motor\spxextrabuilt-in class, 4
- \spxentrydevices.sensor\spxextrabuilt-in class, 3
- \spxentrydevices.servo\spxextrabuilt-in class, 6
- \spxentryget()\spxextradevices.motor method, 5
- \spxentryget()\spxextradevices.sensor method, 3
- \spxentrygetDigital()\spxextradevices.sensor method, 3
- \spxentrygetValueExt()\spxextradevices.sensor method, 4
- \spxentrymemory.clearMemory()
  - \spxentrybuilt-in function, 6
- \spxentrymemory.getMemory()
  - \spxentrybuilt-in function, 6
- \spxentrymemory.setMemory()
  - \spxentrybuilt-in function, 6
- \spxentrymodule
  - \spxentrypython\_vm, 9
- \spxentrymonitor.getKey()
  - \spxentrybuilt-in function, 7
- \spxentrymonitor.keys\spxextrabuilt-in class, 7
- \spxentrymonitor.setText()
  - \spxentrybuilt-in function, 7
- \spxentrypython\_vm
  - \spxentrymodule, 9
- \spxentryPythonVM\spxextraC++ class, 9
- \spxentryPythonVM::PythonVM::getExitInfo\spxextraC++ function, 9
- \spxentryPythonVM::PythonVM::getExitStatus\spxextraC++ function, 9
- \spxentryPythonVM::PythonVM::isRunning\spxextraC++ function, 9
- \spxentryPythonVM::PythonVM::run\spxextraC++ function, 9
- \spxentryPythonVM::PythonVM::stopProgram\spxextraC++ function, 9
- \spxentryS1\spxextradevices.servo attribute, 6
- \spxentryS2\spxextradevices.servo attribute, 6
- \spxentryset()\spxextradevices.motor method, 5
- \spxentryset()\spxextradevices.servo method, 6
- \spxentryStatus\spxextraC++ enum, 9
- \spxentrytime.getTime()
  - \spxentrybuilt-in function, 7
- \spxentrytime.wait()
  - \spxentrybuilt-in function, 7